# How to Build a Ubuntu Linux host under VirtualBox

Texas Instruments

Return to the Sitara Linux Software Developer's Guide

#### Contents

Introduction Download Ubuntu ISO image Download VirtualBox (Vbox) and install Create a New Virtual Machine with VirtualBox Configuring your Virtual Machine under Virtual Box Install Ubuntu on the Virtual Machine Install Guest Additions Sharing Files Between Ubuntu and Windows How to Read a USB SD Card Reader in VirtualBox Switching mouse/keyboard between host and virtual machine. Configuring a Proxy in Ubuntu Additional changes in case apt-get does not work

Note - If behind a company firewall, be sure to set the necessary proxy settings within Ubuntu 10.04 LTS

#### Introduction

This guide shows how to get a virtual Ubuntu Linux machine running with VirtualBox. This process has been successful with Ubuntu 8.04, 9.10 and 10.04 and versions of VirtualBox 3.1.2 and later (currently 3.1.8). Please only use the Ubuntu 10.04 release as this is what is called an LTS (Long Term Support) as there are SDK scripts that will be checking for this release identity.

#### **Requirements**:

• Windows XP host with internet connection, at least 1G of RAM and 40G of free hard drive space.

#### Download Ubuntu ISO image

Get the Ubuntu CD ISO image from: http://www.ubuntu.com (http://www.ubuntu.com)



Click download and the follow instructions to download and save the ISO image (CD image).

#### Download VirtualBox (Vbox) and install

Get	VirtualBox	3.1.8	(Vbox)	from:	http://www.virtualbox.org/wiki/Download_Old_Builds_3_1
Danka a Virtualian	Vir	rtualB	ΟΧ		
	Download	l VirtualBox			
About	Here, you will find li	nks to VirtualBox binaries an	d its source code.		
Screenshots	VirtualBox bi	inaries			
Downloads	The binaries in this	section are all released unde	the VictualBox Personal U	se and Evaluation License (PU	EL). By dow
Documentation	• VirtualBox 3	.1.8 for Windows hosts 🕁	x86/amd64		
End-user docs	• VirtualBox 3	.1.8 for OS X hosts ⇔ Intel	Macs		
Contribute	<ul> <li>VirtualBox 3</li> </ul>	.1.8 for Linux hosts			
Community	• VirtualBox 3	.1.8 for Solaris and OpenS	olaris hosts ⇔x86/amd64		
	<ul> <li>VirtualBox 3</li> </ul>	.1.8 Software Developer K	it (SDK) ⇔ All platforms (re	egistration required)	
	<ul> <li>VirtualBox o</li> </ul>	lder builds			
	See the changelog You might want to	for what has changed. compare the ⇔MD5 sum to	verify the integrity of down	loaded packages.	
	Note: After upgradi	ing VirtualBox it is recommen	ded to upgrade the guest a	additions as well.	
<ul> <li>Click on Downloads</li> <li>Click VirtualBox for V</li> <li>Save to Windows matching</li> </ul>	' link Vindows hosts (currently v. achine	3.1.8)			

NOTE - We have tested with both v3.1.6 and v3.1.8 with no known issues. v3.2.2 however does appear to have an issue when setting up a Shared Folder. For this reason, please be sure to download v3.1.6 or v3.1.8

The Vbox installation will temporarily disrupt the network connection of the Windows host machine. It is a good idea to disconnect from any network drives or remote connections before running the Vbox installation.

- Run the executable to install Vbox
- Accept license and all default settings.

## **Create a New Virtual Machine with VirtualBox**

The following steps are performed with Vbox 3.1.6. The exact steps with other versions may vary slightly

Run Vbox.

Get

- From the initial Vbox GUI click New.
- This will launch a wizard that will step through the creation of the virtual machine. Click Next.

• Type a unique name for the new machine. A good name will include 'Ubuntu' and the Ubuntu version and maybe some other distinguishing info about the machine itself. This will help distinguish the virtual machine from others that may also be under Vbox.

🗘 Create New Virtu	al Machine 🔹 🤶 🔀
VM Name and O	S Type
	Enter a name for the new virtual machine and select the type of the guest operating system you plan to install onto the virtual machine. The name of the virtual machine usually indicates its software and hardware configuration. It will be used by all VirtualBox components to identify your virtual machine. Name Ubuntu 10.04 OS Iype Operating System: Linux Version: Ubuntu
	< <u>B</u> ack <u>N</u> ext > Cancel

• You may want to increase the default RAM size. We have selected 512MB. Click Next.

🍄 Create New Virtua	al Machine	×
Memory		
	Select the amount of base memory (RAM) in megabytes to be allocated to the virtual machine. The recommended base memory size is <b>384</b> MB. Base Memory Size 4 MB 1500 MB	В
	<pre>&lt; <u>Back</u> <u>N</u>ext &gt; Cancel</pre>	

• Keep the default virtual hard disk settings (Create new Boot hard disk). Click Next.

🖤 Create New Virtu	al Machine 🤗 🔀	
Virtual Hard Dis	k	
	Select a hard disk image to be used as the boot hard disk of the virtual machine. You can either create a new hard disk using the <b>New</b> button or select an existing hard disk image from the drop-down list or by pressing the <b>Existing</b> button (to invoke the Virtual Media Manager dialog). If you need a more complicated hard disk setup, you can also skip this step and attach bard disks later using the VM Settings dialog.	
Sun	The recommended size of the boot hard disk is <b>8192</b> MB.     Boot Hard Disk (Primary Master)	
	< <u>B</u> ack <u>N</u> ext > Cancel	

• Select Dynamically expanding storage for the hard disk storage type. Click Next.

NOTE: It is highly recommended to select a hard disk of at least 20GB or higher. Keep in mind that this is the *maximum* size that your virtual hard drive can reach if you've selected the "dynamically expanding storage" option, i.e. it will not immediately take up that many GB of your hard drive. You will need this space for the SDK installation and your development.

Click Finish.

#### **Configuring your Virtual Machine under Virtual Box**

With your virtual machine now created in VirtualBox you need to configure your new machine by highlighting your machine name and clicking on Settings.

Modify the OS Type. Set OS to Linux and Version to Ubuntu. Click Next.

🏶 U	buntu 10.04 -	Settings	
	General	General	
	System Display Storage Audio Network Serial Ports USB Shared Folders	Basic       Advanced       Description         Name:       Ubuntu 10.04         Operating System:       Linux         Version:       Ubuntu         Version:       Ubuntu         Version:       Ubuntu         Select a settings category from the list on the left-hand side and move the mouse over a settings	
		OK Cancel Help	

• If you have not already done so, you may want to increase the default RAM size of your Vbox. We have selected 512MB. Also set CD/DVD-ROM to to highest Boot Order. Click Next.

• Note: Recommended RAM size is 1024MB -- else you may see swap and memory usage complete full causing builds to fail.

😳 Ubuntu 10.04 - :	Settings 🛛 🕐 🔀
General	System
<ul> <li>Display</li> <li>Storage</li> <li>Audio</li> <li>Network</li> <li>Serial Ports</li> <li>USB</li> <li>Shared Folders</li> </ul>	Motherboard       Processor       Acceleration         Base Memory:       512       MB         4 MB       1500 MB         Boot Order:       CD/DVD-ROM         ✓       Floppy         ✓       Hard Disk         Network       Extended Features:         Enable IO APIC       Enable EFI (special OSes only)
	decrease performance. Note: don't disable this feature after having installed a Windows guest operating system!         OK       Cancel       Help

• It may be useful to change the default Video Memory to something more than 12MB. We have selected 64MB.

🔅 Ubuntu 10.04 -	Settings ? 🔀
<ul> <li>General</li> <li>System</li> <li>Display</li> <li>Storage</li> <li>Audio</li> <li>Network</li> <li>Serial Ports</li> <li>USB</li> <li>Shared Folders</li> </ul>	Display         Video       Remote Display         Video Memory:       64         1 MB       128 MB         Extended Features:       Enable 3D Acceleration         Enable 2D Video Acceleration       1000000000000000000000000000000000000
	Select a settings category from the list on the left-hand side and move the mouse over a settings item to get more information.
	OK Cancel Help

Next Add an Attachment to Add a CD/DVD Device and point it to the ubuntu-10.04-desktop-i386.iso. When you Start your virtual machine for the first time, it should boot from the CD/DVD and install Ubuntu 10.04 from this iso file.

🌞 U	buntu 10.04 -	Settings	? 🔀
	General	Storage	
U	Display	Storage Tree	Attributes
9	Storage	😂 IDE Controller	Slot: IDE Primary Slave 💌
₽	Audio	Ubuntu 10.04.vdi	CD/DVD Device: ubuntu-10.04-desktop-i 💌 🗔
₽	Network	💿 ubuntu-10.04-desktop-i386.iso	Passthrough
	Serial Ports	Ploppy Controller	Information
Ø	USB	Empty	Size: 699.44 MB
	Shared Folders		Location: C:\Documents and Settings\a0
			Attached To:
		@ <b>@</b> @	
		Select a settings category from the list on th item to get more information.	e left-hand side and move the mouse over a settings
			OK Cancel Help

Setting a Network Adapter will depend largely on your Windows machine and available network adapters. Enable Network Adapter and select Bridged Adapter for Attached To. If needed expand Advanced to see
more adapters. We would not recommend using a Wireless adapter.

🌼 U	lbuntu 10.04 -	Settings	?×
	General System Display Storage Audio Network Serial Ports USB Shared Folders	Network         Adapter 1       Adapter 2       Adapter 3       Adapter 4         Image: Enable Network Adapter         Attached to:       Bridged Adapter         Name:       Intel(R) 82566MM Gigabit Network Connection         Image: Name:       Intel(R) 82566MM Gigabit Network Connection         Image: Advanced       Adapter Type:         Adapter Type:       Intel PRO/1000 MT Desktop (82540EM)         Mac Address:       080027405853         Image: Cable connected       Image: Cable connected	
		OK Cancel H	telp

• You will need to enable a Serial Port to use minicom within your Linux machine. Enable the Serial Port, set the Port Number to COM1 (typical), Port Mode to Host Device and Port/File/Path to "com1".

😳 Ubuntu 10	.04 - Settings 🔹 🛛 💽 🔀
General System Display Storage	Serial Ports Port 1 Port 2 Enable Serial Port
<ul> <li>Addition</li> <li>Network</li> <li>Serial Port</li> <li>USB</li> <li>Shared For</li> </ul>	Port Number: COM1 V IRQ: 4 I/O Port: 0x3F8 Port Mode: Host Device V Create Pipe Port/File Path: com1
	Select a settings category from the list on the left-hand side and move the mouse over a settings item to get more information.         OK       Cancel       Help

To allow Vbox and Ubuntu to "read" your USB SD Card Reader you need to create a USB Device Filter and select the USB SD reader that is connected to your Windows machine. Enable to USB Controller and the USB2.0 (EHCI) Controller.

NOTE - You must ensure the USB SD Card Reader is connected to your Windows machine BEFORE you run VirtualBox or start your Ubuntu machine. For more information see <u>How to Read</u> a USB SD Card Reader in VirtualBox (http://processors.wiki.ti.com/index.php/How\_to\_Build\_a\_Ubuntu\_Linux\_host\_under\_VirtualBox#How\_to\_Read\_a\_USB.C2.AoSD.C2.AoCard\_Reader\_in\_VirtualBox).

🥮 U	buntu 10.04	- Settings	? 🗙
	General	USB	
	Display	✓ Enable USB Controller	
9	Storage	Enable USB 2.0 (EHCI) Controller	
₽	Audio	USB Device Filters	
P	Network	USB Reader [0205]	ß
	Serial Ports		ß
ø	USB		ß
	Shared Folders		ß
			B
			13
			~
		When checked, enables the virtual USB EHCI controller of this machine. The USB EHCI controller provides USB 2.0 support.	
		OK Cancel Help	<u>,</u>

To enable sharing files between your Linux machine and Windows machine you can use the Share Folders feature of Vbox. For more information, See <u>Sharing Files between Windows XP and Ubuntu Linux (http://pro</u> cessors.wiki.ti.com/index.php/How to Build a Ubuntu Linux host under VirtualBox#Sharing Files Between Ubuntu and Windows).

۲	Ubuntu 10.04 ·	Settings			? 🗙
	General	Shared Folders			
	Display	Folders List			
	gi Dispidy	Name	Path	Access	
	Audio	Machine Folders	C:\Documents an85\My Documents\VBox_Shared	Full	
ſ	Network				2
Ń	👂 Serial Ports				
6	VSB USB				
Ĺ	Shared Folders				
		Select a settings cate item to get more infor	gory from the list on the left-hand side and move the i mation.	nouse over a setting	ъ
			ок	ancel Help	

When you are finished your Vbox should look similar to the screen below which shows all of the settings you configured for your Ubuntu Linux machine in the Details tab.



#### Install Ubuntu on the Virtual Machine

Once configured as seen above, your new virtual machine will display as "Powered Off". Click on the machine to highlight it and then click the Start button.

On Start your virtual machine should boot from CD/DVD and install Ubuntu 10.04 from the ISO file. The steps to install Ubuntu onto the virtual machine will vary depending on the version of Ubuntu. Follow the most reasonable steps to complete the installation. The steps will include the creation of a name for the machine. It can be (but doesn't have to be) the same as the name of the Vbox machine. It helps if the name designates the machine as Ubuntu with a version and a unique identifier. This name will be the hostname on a network.

The steps will also include the creation of a user account. This account will be able to process root access commands with the sudo command . A common username and password is shown below. These names are optional and your choice.

Username: user

Password: useruser

When installation completes, the machine will require a reboot. Since the ISO file has already installed Ubuntu it will ask you to Press Enter to remove the ISO file from the CD/DVD. Press Enter and the reboot will complete booting now from the virtual hard drive which runs Ubuntu.

#### **Install Guest Additions**

With the virtual machine booted, click the Devices menu in Vbox and select "Install Guest Additions...". If you are not logged in as root, you will need to run the autorun.sh script in the Guest Additions software directory; rather than the .run file. Using the autorun.sh script will prompt Linux to ask you for your administrator password. To get to this directory and run the script do the following:

#### 

If the VBOX Additions is not located here, then just change directory (cd) to the mount point that has it.

Accept all the defaults. Guest Additions will allow the Vbox window to be resized. It also allows the mouse to move freely between the host and virtual machine and allows for cut/copy/paste between Windows host and virtual machine. Guest additions are also required for file sharing between the Windows and the Linux system.

#### **Sharing Files Between Ubuntu and Windows**

VirtualBox has a Shared Folders feature which you need to setup before starting the Ubuntu image. In Virtual Box select your Ubuntu image and click Settings. At the bottom you will see Shared Folders. Specify (or create) the Windows folder you want to share with Ubuntu. Give the shared folder a name. It is a good idea to use the same folder name for both Windows and Ubuntu.

Using Shared Folders with VirtualBox requires that the VirtualBox Guest Additions has been installed. Also, Ubuntu updates often wreck the VirtualBox Guest Additions settings. If folder sharing stops working after a Ubuntu update, reinstall Guest Additions.

😵 Sun Virt	ualBox		
File Machin	ne Help		
Virt	Image: Help         Image: Help         Image: Ubuntu 10.04 -         Image: General         Image: System         Image: System         Image: Display         Image: Displ	Settings         Folders List         Name       Path         Access         Wachine Folder         Vbox_shall         Folder Path:         C:\Docuuments\Vbox_shared         Folder Name:         Vbox_shared         Read-only         OK         Cancel         Select a settings category from the list on the left-hand side and move the mouse over a setting tem to get more information.	
		OK Cancel Help Intel(R) 82566MM Gigabit Network C	ionnection)

#### Nomenclature:

- <user> the Username of your Ubuntu machine
- vbox\_shared the Shared Folder name for both Windows and Ubuntu

Now Start your Ubuntu machine and from Applications-Accesories-Terminal in Ubuntu create a folder on your Desktop of the same name: vbox\_shared.

mkdir /home/ <user>/Desktop/vbox_shared</user>	
This line "connects" or mounts your VirtualBox Shared Folder "vbox_shared" to the folder you just created on your Ubuntu Desktop called /home/user/Desktop/vbox_shared.	
sudo mount -t vboxsf vbox_shared /home/ <user>/Desktop/vbox_shared</user>	

Now you can simply copy files back and forth between the vbox\_shared folder from either Ubuntu or Windows. You will see the same file(s) appear in the vbox\_shared folder in the other OS.

If you reboot or shutdown your Ubuntu machine you will need to sudo mount -t... your Shared Folder again as seen in the second step above. You can do this automatically by <u>Creating a Init Script in Ubuntu (http://proce</u> ssors.wiki.ti.com/index.php/Auto\_Start\_a\_Script\_in\_Ubuntu) and adding the sudo mount -t... line to it. On rebooting your Ubuntu machine, you will find the vbox\_shared folder is mounted automatically each time.

#### How to Read a USB SD Card Reader in VirtualBox

Prior to beginning this process, if you haven't already, shutdown the VirtualBox session, AND restart your computer.

1. In Settings for your virtual machine, be sure to Add a USB Device Filter and select the USB SD Reader that Windows "sees".

- 1. Click the Settings button under Vbox for the virtual machine. Click USB in the left hand pane of the Settings window. A button on the right side of the window has a green plus symbol. If the mouse is hovered over this button a flag will read "Add Filter From Device". Click this button and select the card reader from the list of choices.
- 2. Before you run VirtualBox and Start your Linux virtual machine, be sure that Windows first "sees" USB SD Card Reader. Otherwise, Ubuntu will never "see" it.
- 3. When you Start your virtual machine, Ubuntu will mount any active partitions found on the SD card. Depending on the SD card you may see folders or partitions open on the Ubuntu Desktop. Also you can run "df -hT" in a Terminal to print details about the partitions.

#### Switching mouse/keyboard between host and virtual machine.

When you left click inside your Linux virtual machine, by default your keyboard and mouse will remain focused within the Linux machine until you press the Right CTRL button. This will allow you to go back to your Windows desktop.

To use your mouse and keyboard across both Windows and Linux without using Right CTRL to switch, install the VirtualBox Guest Additions as described below.

### **Configuring a Proxy in Ubuntu**

If your network is behind a firewall you will need to configure the network proxy for Ubuntu in order to successfully download the applications required to complete your development environment or to browse the Internet on your Linux Host machine.

To configure the network proxy in Ubuntu go to System-Preferences and click Network Proxy as seen below.



As seen in the image below, click Manual Proxy Configuration. Specify the HTTP proxy server used by your company. You may find this information under your Windows OS inside the Internet Explorer Network Connections. On your host machine, open Internet Explorer. Go to, 'Tools', 'Internet Options', in the 'Connections' tab, click 'LAN settings'. Copy the proxy address shown. Be sure to specify the port.

Make sure you check "Use the same proxy for all protocols". Also be sure to click "Apply System-Wide". Then Close

Network			
All Settings Network			
1 Wired		оху	
Retwork proxy	N N	one	
	Method M	anual	
	HTTP Proxy	utomatic	
	HTTPS Proxy w	ww.proxyserver.com	80 🗕 🕂
	FTP Proxy w	ww.proxyserver.com	80 🖛 🕂
	Socks Host w	ww.proxyserver.com	80 💻 🖶
		Apply system wide	

Finally you will be asked to entered your password in order to set your network proxy information. This is typically the same password you used to log into Ubuntu on boot.

R	System policy prevents setting proxy settings An application is attempting to perform an action that requires privileges. Authentication is required to perform this action			
	Password:			
+ Deta	lls			
	Cancel Authenticate			

You should now be able to browse the Internet using Firefox within Ubuntu. Note: If you are still unable to browse the internet, open Firefox. Go to, 'Edit', 'Preferences', under the 'Advanced' tab, click 'Network', then click 'Settings'. Make sure the proxy address is copied into the field, 'Automatic proxy configuration URL'.

### Additional changes in case apt-get does not work

In some case, sudo apt-get <package-name> may not work. In such a case, sources.list should be updated to add http://archive.ubuntu.com/ubuntu.

\$ vim /etc/apt/sources.list
"deb-src <u>http://archive.ubuntu.com/ubuntu</u> lucid restricted main #Added by software-properties"
\$ sudo apt-get -y update

Also verify or create the file /etc/apt/apt.conf, the following lines need to be present: proxy server name needs to be replaced with server name:

/etc/apt/conf - should have these lines, use "sudo vi" or "sudo gedit" to edit the file depending on your preference,

Acquire::http::proxy "http:// proxy server name :80/"; Acquire::ftp::proxy "ftp:// proxy server name :80/"; Acquire::https::proxy "https:// proxy server name :80/";

Engage in the Tics: The additional stress of the monoidige, explore liber Tics: The additional stress of the monoidige, explore liber and hap tarting additional with dow impresent	<ul> <li>{{ <ol> <li>switchcategory:MultiCore</li> <li>For technical support on MultiCore devices, please post your questions in the C6000 MultiCore Forum</li> <li>For questions related to the BIOS MultiCore SDK (MCSDK), please use the BIOS Forum</li> </ol> </li> <li>Please post only comments relate to the article How to Build Ubuntu Linux host under VirtualBox here.</li> </ul>	Keystone=  For technical support on MultiCore devices, please post your questions in the C6000 MultiCore For questions related to the BIOS MultiCore SDK (MCSDK), please use the <u>BIOS Forum</u> Please post only or comments related to the article How to Build a Ubuntu Linux host under VirtualBox here.	C2000=For technical support on DaVinci=For the C2000 technical please support on post your DaVincoplease questions post your on <u>The</u> questions on <u>C2000</u> The DaVinci Forum. Forum. Please Please post only post only comments comments about the about the article <b>How to</b> article <b>How Build a</b> <b>y to Build a Ubuntu Linux</b> <b>buntu host under</b> <b>a Linux host VirtualBox</b> <b>here</b> .	MSP430=For technical support on MSP430 please post your questions on The MSP430 Forum. Please post only comments about the article How to Build a Ubuntu Linux host under VirtualBox here.	OMAP35x=For technical support on OMAP please post your questions on <u>The OMAP</u> <u>Forum</u> . Please post only comments about the article <b>How to</b> <b>Build a</b> <b>Ubuntu Linux</b> <b>host under</b> <b>VirtualBox</b> here.	OMAPL1=For technical support on OMAP please post your questions on The OMAP Forum. Please post only comments about the article How to Build a Ubuntu Linux host under VirtualBox here.	MAVRK=For technical support on MAVRK please post your questions on <u>The</u> MAVRK <u>Toolbox</u> Forum. Please post only comments about the article How to Build a Ubuntu Linux host under VirtualBox here.	For technical support please post your questions at <u>http://e2e.ti.com</u> . Please post only comments about the article <b>How to Build a</b> <b>Ubuntu Linux host</b> <b>under VirtualBox</b> here. }}
			Lin	(S				
	Amplifiers & Linear       D         Audio       H         Broadband RF/IF & Digital Radio       Ir         Clocks & Timers       L         Data Converters       P	DLP & MEMS	<ul> <li><u>ARM Processors</u></li> <li><u>Digital Signal Processors</u></li> <li><u>Microcontrollers (MCU)</u></li> <li><u>OMAP Applications Proce</u></li> </ul>	(DSP) <u>Switch</u> <u>Tempe</u> <u>Wirele</u> <u>Ssors</u>	es & Multiplexers rature Sensors & C ss Connectivity	control ICs		

Retrieved from "https://processors.wiki.ti.com/index.php?title=How\_to\_Build\_a\_Ubuntu\_Linux\_host\_under\_VirtualBox&oldid=114195"

This page was last edited on 24 July 2012, at 15:23.

Content is available under Creative Commons Attribution-ShareAlike unless otherwise noted.